

THE SETTINGS CONTROL 2 DEFAULT SETTINGS AND THE WAY STDOSE CASES FILES ARE NAMED.

The screenshot shows a 'Settings' dialog box with a green title bar and a close button (X) in the top right corner. The dialog is divided into four main sections, each with a title and a group box border:

- Default Analyst Name:** Contains the text 'Set default to use for analyst name'. It has three radio buttons: 'System name' (unselected), 'User entered name' (selected), and 'Always prompt for name' (unselected). The 'User entered name' option is followed by a text input field containing 'Dose Analyst'. Above the 'System name' option, the text 'HOLDEN' is displayed.
- Default Inhalation Dose Coefficients:** Contains two radio buttons: 'ICRP 26/30' (selected) and 'ICRP 60/72' (unselected).
- Case File Naming:** Contains two radio buttons: 'User entered' (selected) and 'Based on case title' (unselected). Below these is a text input field for 'Optional prefix:' containing '[TR]', followed by the text '(maximum 6 characters)'. A paragraph of text below states: 'File name is automatically created; no user naming is allowed. The prefix can optionally be added at save time to indicate file status (e.g. reviewed or approved).'
- Load Case at Startup:** Contains an empty text input field followed by a 'Browse' button. Below this are two radio buttons: 'Load the above case at startup' (unselected) and 'Do not load a case at startup' (selected).

On the right side of the dialog, there are three buttons: 'OK', 'Cancel', and 'Help'.

THE ANALYST NAME WILL APPEAR ON THE CASE SUMMARY REPORT



The screenshot shows a dialog box titled "Default Analyst Name". Inside, there is a label "Set default to use for analyst name" followed by three radio button options. The first option is "System name" with the text "EVE" next to it. The second option is "User entered name" which is selected, and it has a text input field containing "Steve Talister (800) 666-4321". The third option is "Always prompt for name".

Default Analyst Name

Set default to use for analyst name

☐ System name EVE

☒ User entered name

☐ Always prompt for name

- This is only the default and can be changed at calculation time
- Can enter any text but suggest name and maybe some contact information such as phone number or email address.
- This kind of labeling can be very important in long events where multiple people are running the model and generating products.

SET THIS TO BE THE INHALATION DOSE COEFFICIENTS THAT ARE NORMALLY USED BY YOUR ORGANIZATION FROM DOSE ASSESSMENTS.

Default Inhalation Dose Coefficients

☒ ICRP 26/30

☐ ICRP 60/72

- This is only the default and can be changed at calculation time
- Most of US still uses ICRP 26/30, but the new EPA Protective Action Guidelines are published for interim use and incorporate ICRP 60/72

THIS SETTING DETERMINES HOW THE PROGRAM ACTS WHEN IT COMES TIME TO SAVE AN STDOSE CASE.

Case File Naming

☒ User entered

☐ Based on case title

Optional prefix: (maximum 6 characters)

File name is automatically created; no user naming is allowed. The prefix can optionally be added at save time to indicate file status (e.g. reviewed or approved).

Generate file name from case title

Destination folder for the saved case

Case file name that will be used

☐ Add prefix - [TR] ☒ Append date ☒ Append time

- With the *User entered* option, you always get to enter any name you like just as with most software.
- Basing it on the case title enforces some structure to the name used.